GrADS reference card version 1.7

compiled by Karin Meier-Fleischer, DKRZ (beratung@dkrz.de (GrADS Version 1.7 beta 7)

GrADS program executables

grads link to one of the following executables	
gradsnc grads with netCDF enabled	
gradshdf grads with HDF enabled gradsc grads "classic", without netCDF/HDF/Athena GUI, etc.	

Command line options

Program: grads [-lbpC] [-c 'command']		
-c 'command'	execute 'command' when starting GrADS	
-b	run grads in batch mode. No graphics output window is opened.	
-1	run grads in landscape mode. The orientation question is not asked.	
-р	run grads in portrait mode. The orientation question is not asked.	
-C	enable automatic setting of century for years < 100	

General settings

help gives a summary list of operations		
set grads on off	off enable/disable display of the GrADS logo	
set display <option <color="">></option>		
	sets the mode of the display. options are:	
grey greyscale	scale sets the mode to greyscale.	
color shading and contouring is done with rainbow colors. Default.		

set frame <option></option>		
	control the frame on a plot. options are:	
on	plots a rectangular frame around clipped region	
off	plots no frame	
circle	plots a rectangular frame for lat-lon projections, plots a circular fram- for a polar plot at the outermost latitude. Whole hemisphere plots only	

set background ic	ekground ic set background color to color or color index ic	
display expression display data via the graphics output window; the simplest express a variable abbreviation		
open filename	open descriptor file	
sdfopen file.nc <template #timesteps=""></template>		
	opens a netCDF or HDF-SDS format file that conforms to the COARDS conventions. The optional arguments are for string a time-series of files together as one GrADS data object.	
xdfopen file	opens a non-COARDS-conformant netCDF or HDF-SDS file via a data descriptor file similar to those used with the 'open' command.	
close file#	close the last descriptor file opened.	
set dfile number change to descriptor file number for current file		
define var=expr var=expr	create new variable, which then can be used in subsequent expressions	
undefine var	free the resources used by the defined variable	

modify varname <time type=""></time>		
	define variable, which is climatological. varname is the defined grid.	
	Time types are:	
seasonal	monthly or multi-monthly means	
diurnal	diurnal over some time period less than a day	

query <option> q <option></option></option>	<option> <option> query options are:</option></option>	
config	list GrADS configuration information	
files	lists open files	
file n gives info on particular file		
define lists currently defined variables		
dims gives current dimension environment		
gxinfo gives graphics environment info		
shades gives colors and levels of shaded contours		
pos waits for mouse click, returns the position		

time	gives info about time settings	
fwrite	print name of fwrite ouput file	
string s	gives the width of string s	
defval v1 i j	gives the value of a defined variable v1 at point i,j	
udft	list the user defined function table	
lats	state of the GrADS-LATS interface	
xy2w v1 v2	XY coords to world coords	
xy2gr v1 v2	XY coords to grid coords	
w2xy v1 v2	world coords to XY coords	
w2gr v1 v2	world coords to grid coords	
gr2w v1 v2	grid coords to world coords	
gr2xy v1 v2	grid coords to XY coords	
ll2xy lon lat	LON/LAT coords to XY coords	
pp2xy ppx	page coords to XY coords	
ppy		
set imprun script	automatically executes script before every display command	
run file-name <params></params>		

•		
set imprun script automatically executes script before every display command		
run file-name <params></params>		
	load and run a GrADS script (with parameters)	
exec fname <arg0arg9></arg0arg9>		

	exec manie \aigo,,aig>>		
		executes a sequence of GrADS commands from file fname. If a clear command is encountered, GrADS waits until enter is pressed before clearing and continuing with command processing	
	clear <option> c <option></option></option>		
	events	flush event buffer	
graphics clear graphic, not widgets		clear graphic, not widgets	

BP	8	
hbuff	clear display buffer, when in double buffer mode	
reset <option> initializes GrADS to its initial state with following exceptions: 1) No files are closed. 2) No defined objects released. 3) The 'set display' settings are not modified. Op events: graphics: hbuff; norset</option>		
reinit	same as reset, and in addition closes all open files and releases all defined objects	
quit - to leave GrADS		
!shell-command	runs a shell command on GrADS command line. The output will not be returned to the script, only displayed.	

Dimension environments

set lon	val1 <val2></val2>	sets longitude to vary from val1 to val2
set lat	val1 <val2></val2>	sets latitude to vary from val1 to val2
set lev	val	sets the level to val - fixed dimension
set t	val1 <val2></val2>	sets time to the "val" time in the data set
set x	val1 <val2></val2>	set x values or fix it to one value
set y	val1 <val2></val2>	set y values or fix it to one value
set z	val1 <val2></val2>	set z values or fix it to one value

Page control

set vpage	off	real page is equal to "virtual page"; default state
set vpage	xmn xmx ymn ymx	defining one "virtual" page
set parea	xmn xmx ymn ymx	control the area within the virutal page

Graphic types

set gxout graphic-type	where graphic-type could be:
bar	Bar chart
barb	Plot wind barb at station
contour	Contour plot
errbar	Error bar
fgrid	specific value grid fill plot
findstn	Find closest station to x,y point
fwrite	Write data to file instead of displaying
grfill	Filled grid boxes
grid	Grid boxes with values
line	Line graph
linefill	Color fill between two lines
model	Plot station model

scatter	Scatter graph plot
shaded	Shaded contour plot
stat	Display information about data
stream	Streamline plot
tserwx	Plot time series of weather symbols at a point (1-D sta-
	tion)
tserbarb	Plot time series of wind barbs at a point (1-D)
value	Plot station values
vector	Vector wind arrows
wxsym	Plot weather symbols at station

Default colors, line styles and marker types

		-	-
color	colors used by many settings (i.e. ccolor, line, string button, clopts, lfcols,):		
0	black	1	white
2	red	3	green
4	blue	5	cyan
6	magenta	7	yellow
8	orange	9	purple
10	yellow/green	11	med.blue
12	dark yellow	13	aqua
14	dark purple	15	grey

line styles used by many settings (i.e. cstyle, line, mpt, map, grid,):			
0	0 none 1 solid		
2	long dash	3	short dash
4	long short dash	5	dots
6	dot dash	7	dot dot dash

marker types used by many settings (i.e. cmark, mark,):			
0	none	1	cross
2	open circle	3	closed circle
4	open square	5	closed square
6	X	7	diamond
8	triangle	10	open circle with vertical line
9	none	11	open oval

Graphics options

set clip xlo xhi ylo yhi	clipping area for drawing graphics primitives
set ccolor index	sets the contour color to index, see Default colors and line
	styles. You can also issue:
	rainbow - rainbow color sequence
	revrain - reversed rainbow color sequence
set cstyle style	sets the contour or line style, see Default colors and line
	styles. (gxout = contour, only style 1,2,3 and 5 available).
set cmark marker	sets line marker, see Default colors and line styles .
set cterp on off	turns spline smoothing on or off
set clab on off forced string	auto
	controls contour labeling
set clopts col <thick <size="">></thick>	contour line options
set clskip val	skip val contour lines when labelling
set cthick thckns	sets the line thickness for the contours [1-10]
set csmooth on off linear	interpolate to a finer grid using cubic or linear interpolation
set cint value	sets the contour interval to the specified "value"
set cmax value	contours not drawn above this value
set cmin value	contours not drawn below this value
set clevs lev1 lev2	sets specified contour levels
set ccols col1 col2	sets specified color for clev levels
set line col <style> <thick></th><th>sets current line attributes. thickness range 1 - 6 (see</th></tr><tr><th></th><th>Default colors and line styles).</th></tr><tr><th>set lfcols col1 col2</th><th>set color below and above lines (gxout linefill)</th></tr><tr><th>set black off val1 val2</th><th>contours not drawn within this interval</th></tr><tr><th>set rbcols c1 c2 <c3 cn></th><th>specifies a new 'rainbow' color sequence</th></tr><tr><th>set rbcols <auto></th><th>built in rainbow sequence is used</th></tr><tr><th>set rbrange low high</th><th>range of values used to determine which values acquire which rainbow color</th></tr><tr><th></th><th></th></tr></tbody></table></style>	

set grid on off <style> <color> horizontal vertical</th></tr><tr><th></th><th>draw grid lines using the specified options or not</th></tr><tr><th>set bargap val</th><th>sets the gap between bars in percent</th></tr><tr><th>set barbase value bottom top</th><th>bar rises from or falls from value</th></tr><tr><th>set baropts filled outline</th><th>bar outlined or filled; default: filled</th></tr><tr><th>set dignum number</th><th>number of digits after the decimal place</th></tr><tr><th>set digsize size</th><th>size (in inches, or plotter units) of the numbers</th></tr><tr><th>set arrlab on off</th><th>set arrow labeling on or off</th></tr><tr><th>set arrscl size <magnitude></th><th>specifies arrow length scaling</th></tr><tr><th>set arrowhead size</th><th>specifies arrow head size</th></tr><tr><th>set fgvals v1 c1 <v2 c2></th><th>fgrid output type treats the grid values as rounded integers, and will shade a specified integer valued grid with the specified color.</th></tr><tr><th>set zlog on off</th><th>sets log scaling of the Z dimension on or off</th></tr><tr><th>set strmden value</th><th>specifies the streamline density, where value is from 1 to 10. Default: 5</th></tr><tr><th>set stnopts <dig3> <nodig3></th><th>plot the number in the slp location as a three digit number with only the last three digits of the whole number plotted</th></tr><tr><th colspan=2>set mdlopts noblank blank dig3 nodig3</th></tr><tr><th></th><th>plot the number of the model data as a three digit</th></tr><tr><th>set stid on off</th><th>controls wether the station id is displayed next to the val-</th></tr><tr><th></th><th>ues or not</th></tr><tr><th>set wxcols c1 c2 c3 c4 c5 c6</th><th>set colors for weather symbols c1 - c6</th></tr><tr><th></th><th></th></tr></tbody></table></style>	

Axis labeling/Annotation/labeling

Axis labeling/Annotation	niviabelling
set xaxis start end <incr></incr>	specifies the axis is to be labeled
set yaxis start end <incr></incr>	specifies the axis is to be labeled
set xlevs lab1 lab2	specifies the label levels to plot for the X axis
set ylevs lab1 lab2	specifies the label levels to plot for the Y axis
set xlint interval	specifies the label interval of the X axis
set ylint interval	specifies the label interval of the Y axis
set xyrev on	reverses the axes on a plot
set xflip on	flips the order of the horizontal axis
set yflip on	flips the order of the vertical axis
	controls and/or draws X axis label
	controls and/or draws Y axis label
set xlabs lab1 lab2	abel the x axis with lab1, lab2, lab3,
set ylabs lab1 lab2	label the y axis with lab1, lab2, lab3,
draw xlab string	draw x axis label
draw ylab string	draw y axis label
set xlopts col <thick <size="">></thick>	
set ylopts col <thick <size="">></thick>	
set xlpos offset side	controls position of x axis labels. Where offset - in inches; side - b or t (bottom or top)
set ylpos offset side	controls position of y axis labels. Where offset - in inches; side - r or l (right or left)
set zlog on off swap unde	fine
	sets log scaling of the Z axis
set annot col <thick></thick>	sets color and line thickness for the above 3 draw commands
set vrange vlo vhi	Set range for plotting 1-D or scatter plots; range of the variable values for y-axis scaling
set vrange2 vlo vhi	Set range for plotting 1-D or scatter plots; range of the variable values for x-axis scaling
set missconn on off	lines will be connected across missing data
draw title string	draw title at top of graph

Map projections/drawing

set mproj proj	sets current map projection. Keywords are:
latlon	Lat/lon projection with aspect ratio maintained. Default.
scaled	latlon projection where aspect ratio is not maintained. The plot fills the plotting area.
nps	north polar stereographic
sps	south polar stereographic
robinson	Robinson projection
orthogr	Orthographic projection
mollweide	Mollweide projection
lambert	Lambert conformal conic projection

same as scaled, but no map is drawn and lables are not interpreted as lat/lon labels

set mpt type off	< <col/> <style> <thick>></th></tr><tr><th></th><th>command to control map background behavior. type is the map type; it can be a number from 0 to 255, or it can be an asterick (*) to indicate this command applies to all the type values. The color can be set to -1, which indicates to GrADS to use the set map settings for this map type, rather than the settings specified by the set mpt command.</th></tr><tr><th>set mpvals off lr</th><th>nmn lnmx ltmn ltmx</th></tr><tr><th></th><th>sets reference longitudes and latitudes for polar stereogr. plots</th></tr><tr><th>set mpdset lowre</th><th>s mres hires nmap</th></tr><tr><th></th><th>mres and hires have state and country outlines. nmap covers only North America. Default:lowres.</th></tr><tr><th colspan=2>set map auto color <style <thick>></th></tr><tr><th></th><th>draws the map background using the requested line attributes or auto mode</th></tr><tr><th>set mpdraw on </th><th>off</th></tr><tr><th></th><th>if off, does not draw the map background</th></tr><tr><th>set grid on off <</th><th>style <col>> horizontal vertical</th></tr><tr><th></th><th>draw or do not draw lat/lon lines on polar plots using the specified color and linestyle</th></tr><tr><th>set poli on off</th><th>selects whether you want political boundries drawn for the mres or hires map data sets. Default is on</th></tr></tbody></table></style>

Graphic primitives

draw line x1 y1 x2 y2	draws a line from x1, y1 to x2, y2 using current line drawing	
	attributes	
	draws an unfilled rectangle	
draw recf xlo ylo xhi yhi	draws a filled rectangle	
draw mark marktype x y size		
	draws a marker. Marker types (see Default colors and line styles).	
draw polyf x1 y1 x2 y2 xn yn		
	draw a filled polyline, where xn=x1 and yn=y1	
draw wxsym symbol x y size <color <thickness="">></color>		
	Draws the specified wx symbol at the specified location	

String primitives

• .		
set string col <justification> <thick> <rotation></rotation></thick></justification>		
	sets string drawing attributes. Justification: 1 - left; c - center; r - right; tl - top left; tc - center top; tr - right top; bl - bottom left; tc - center bottom; tr - right bott. Roation: 90 - counterclockwise, -90 - clockwise	
set strsiz width <height></height>	sets the string character size	
draw string x y string	draws the character string at the x,y position	
draw title string	draw a title 'string' on top of the graph	

Color settings

set rgb num red green blue	defines new colors within GrADS, and assigns them to a new
	color number.color-number num must be a value between 16
	and 99 (0 to 15 are predefined)

Font settings

. on cominge		
set font number	change to font number [0-5]	

Widgets

set button 1 bcol1 bcol2 bcol3 0 fcol1 fcol2 fcol3 thickness		
	set button colors. 1 - "on" state; 0 - "off" state	
draw button number x y width height string		
	draws a button on position x,y with the attributes	
redraw button number 0 1		
	redraws button number; 1 - "on"; 0 - "off"	
set rband wn mode x1 y1 x2 y2		
	rubber banding. wn = widget #; mode = box or line	
	x1, y1 = lowest point in x/y page units	
	x2, $y2$ = highest point in x/y page units	

draw dropmenu number x y width height text

display a dropmenu similar to 'draw button' command widget number (0 to 64); x and y are the center location for the 'base' of the dropmenu; width and height are the size of the 'base' of the dropmenu.

Double buffering

	sets double buffer mode on or off
swap	swaps buffers, when double buffer mode is on

Animation

set looping on off control animation; set animation on or off	
set loopdim x y z t animate through x,y,z or t; default: t	
set loopincr incr	set looping increment

Hardcopy output

enable print fname enables the print command to the given file fname	
print	copy the contents of current display into a file in a metacode format
disable print	close print output file
outxwd file output the graphicw window to a file in the X windows dump form	
wi file.format	output to a file with format (using ImageMagick), e.g. wi test.gif

Create/Write a grid file

set fwrite fname	output grid fname; if not set, fname=grads.fwrite
set gxout fwrite	enables grid file output
disable fwrite	close output grid file

Mathematical Functions

abs(expr)	absolute value of result of expr. Operates on gridded and station data	
acos(expr)	applies the cos ⁻¹ function to the result of expr	
asin(expr)	applies the sin ⁻¹ function to the result of expr	
atan2(expr1,expr2)	applies the tan^{-1} function to the result of the two expr, using $tan\theta = y/x$	
cos(expr)	takes the cosine of the expr	
exp(expr)	performs the ex operation, where expr is x. gridded and station data	
gint(expr)	general integral, same as ave except do not devide by the total area	
log(expr)	takes the natural logarithm of expr	
log10(expr)	takes the logarithm base 10 of the expr	
pow(expr1,expr2)	raises the values of expr1 to the power of expr2	
sin(expr)	takes the sine of the provided expr (in radians)	
sqrt(expr)	takes the square root of the result of the expr	
tan(expr)	takes the trigonometric tangent of the expr	

Averaging Functions

ave(expr,dexpr1,dexpr2<,tinc<,flags>>)	
	generalized averaging function. expr is averaged through the dimension range specified by dim1 and dim2
aave(expr,xdim1,xdim2,ydim1,ydim2)	
	does area average. xdim1 and xdim2 must be for lon or x, ydim1 and ydim2 must be for lat or y (e.g. aave(t,lon=0,lon=180,lat=0,lat=90))
mean(expr,dexpr1,dexpr2<,tinc<,flags>>)	
	same as ave, except that area weighting is disabled
amean(expr,xdim1,xdim2,ydim1,ydim2)	
	same as aave, except that area weighting is disabled
vint(psexpr,expr,top)	performs a mass-weighted vertical integral in mb pressure coordinates, where: exprexpression for quantity to be integrated psexpr expression yielding the surface pressure, in mb, which will be used to bound the integration on the bottom topconstant, giving the bounding top pressure, in mb. This cannot be provided as an expression

Grid Functions

cons	st(expr,const<,flag>)	function allows you to set various parts of a grid to a constant
mas	skout(expr,mask)	whenever the mask values are less than zero, the values in expr
		are set to the missing data value
skip	o(expr,skipx,skipy)	sets alternating values of the expr to the missing data value. This function is used while displaying wind arrows or barbs to thin the number of arrows or barbs

Filtering Functions

smth9(expr)	performs a 9 point smoothing to the gridded result of expr

Finite Difference Functions

- J:ee/ J:	
caintexpr.aim	performs a centered difference operation on expr in the direction specified
(<u>F</u>)	
	by dim
	Toy unii

Meteorological Functions

tvrh2q(tvexpr,rhexp	given virtual temperature and relative humidity, tvrh2q returns specific humidity, q, in g/g
tvrh2t(tvexpr,rhexp	 given virtual temperature and relative humidity, tvrh2t returns the temperature in degrees Kelvin

Special Purpose Functions

when time is varying dimension in the dimension environment, tloop function
evaluates the expr at fixed times, then constructs the time series to obtain a
final result that is the time varying

Vector Functions

	calculates the vertical component of the curl (i.e.vorticity) at each grid pointusing finite differencing on the grids provided
hdivg(expr1,expr2)	calculates the horizontal divergence using the finite differencing
mag(uexpr,vexpr)	performs the calculation: sqrt(uexpr*uexpr+vexpr*vexpr)

Station Data Functions

Station Bata i anotions		
gr2stn(grid_expr,stn_expr)	performs an interpolation from grid space back to station loca-	
	tions	
oacres(grid_expr,stn_expr<	oacres(grid_expr,stn_expr<,radii <first guess="">>)</first>	
	a Cressman objective analysis is performed on the station data to yield a gridded result representing the station data	
stnave(expr,dexpr1,dexpr2<,-m cnt>)		
	takes an average of station data over time	
stnmin(expr,dexpr1,dexpr2	!<,-m cnt>)	
	examines a time series of station data and returns the minimum value encountered for each station	
stnmax(expr,dexpr1,dexpr2<,-m cnt>)		
	examines a time series of station data and returns the maximum value encountered for each station	

Create PostScript files

Program: gr	xps [-c] [-r] [-d] [-i mfile] [-o ofile]
converts the GrADS meta file into a PostScript file. Command line options:	
-с	color on a white background (=old gxpscw)
-r	color on a black background (=old gxpsc)
-d	add ctrl-d to the end of the file, useful if printing on HP 1200C/PS printer
-i mfi	le where mfile is the name of the input GrADS meta file
-o ofil	where ofile is the name of the output PostScript file

Program: gxeps [-1][-2][-a | -1][-c][-r][-d][-L][-n][-s][-v] [-i mfile] [-o ofile]

converts the GrADS meta file into a PostScript file. Command line options:

- PostScript Level 1 output
- PostScript Level 2 output -2
- DIN A4 paper size
- color on a white background
- add ctrl-d to the end of the file, useful if printing on HP 1200C/PS printer
- US letter paper size
- ask for a label to be printed on the plot ask for a note to include in postscript file header -n
- color on a black background -r
- add a file & time stamp
- verbose
- -i mfile where mfile is the name of the input GrADS meta file
 - where ofile is the name of the output PostScript file

Create GIF files

Program: gxgif [-i mfile] [-o ofile]

converts the GrADS meta file into a GIF file. Command line options:

- -i mfile where mfile is the name of the input GrADS meta file
- -o ofile where ofile is the name of the output GIF file

Variables

complete specification for a variable name

abbrev.file#(dimexpr,dimexpr,...)

abbrev is the abbreviation for the variable as specified in the data descriptor file file# is the file number that contains this variable. The default initially is 1. dimexpr is a dimension expression that locally modifies the current dimension environment.